


# NenuFAR raw data with NenuRaw

**Raw ~~meat~~ inside!!  
data**



# NenuFAR waveform data with NenuRaw

**Jump on your favourite Nancep machine**

**Source the python3.8 environment of NenuRaw**

```
> source /home/lbondonneau/PSRpy3env/bin/activate
```



# NenuFAR waveform data with NenuRaw (spectrum)

## Python 3 script to plot the spectrum

```
> python3.8 /cep/lofar/pulsar/NenuRaw/demo/demo_spectrum.py
```

```
#!/usr/bin/env python3
```

```
from NenuRaw import dynspec_utils
from NenuRaw import wav_utils
```

**Import useful libraries**

```
if __name__ == "__main__":
```

```
    # wavfile (GUPPI or RAWTF format)
```

```
    files = ['/data/bf2/nenufar-pulsar/ES03/2020/05/B0834+06_D20200510T1700_58979_250507_0069_BEAM1.0000.raw']
```

```
    # initialisation of the Dynspec object containing the methodes
```

```
    my_spectra = dynspec_utils.Dynspec(files,
```

```
        verbose=True,
```

```
        freq_start=0,
```

```
        freq_end=99,
```

```
        start=10, #start time in sec
```

```
        end=12 #stop time in sec
```

```
    )
```

**Freq selection**

**Time selection**

```
    # force dm to 0 pc cm-3 or will use the dm from the header in PSR obs
```

```
    my_spectra.dm = 0
```

```
    # execution of the processing method in the Fourier domain creating 64 sub-
```

```
    # and conversion to total intensity with time integration of 100 ms
```

```
    my_spectra.fourier_computation(fftlen=64, ds_ms=100, pol="I") #I, Q, U, L,
```


**195/64 = 3 kHz    100 ms    Total intensity**

```
    #plot spectrum
```

```
    my_spectra.clean(threshold=10) # clean with threshold=10
```

```
    my_spectra.plot_spectra()
```



**Plot spectra**



# NenuFAR waveform data with NenuRaw (spectrum)

## Python 3 script to plot the spectrum

```
> python3.8 /cep/lofar/pulsar/NenuRaw/demo/demo_spectrum.py
```



# NenuFAR waveform data with NenuRaw (dynamic spectrum)

## Python 3 script to plot the dynamic spectrum

```
> python3.8 /cep/lofar/pulsar/NenuRaw/demo/demo_storm_dynspectrum.py
```

```
if __name__ == "__main__":  
    # wavfile (GUPPI or RAWTF format)  
    files = ['/datafb2/nenufar-pulsar/ES03/2020/05/B0834+06_D20200510T1700_58979_250507_0069_BEAM1.0000.raw']  
  
    # initialisation of the Dynspec object containing the methodes  
    my_spectra = dynspec_utils.Dynspec(files,  
                                       verbose=True,  
                                       freq_start=0, #min freq allow  
                                       freq_end=99, #max freq allow  
                                       start=10, #start time in sec  
                                       end=20 #stop time in sec  
                                       )
```

```
# force dm to 0 pc cm-3 or will use the dm from the header in PSR obs  
my_spectra.dm = 0
```


```
# execution of the processing method in the Fourier domain creating 1 sub  
# and conversion to total intensity with time integration of 50 ms  
my_spectra.fourier_computation(fftlen=1, ds_ms=10, pol="I") #I, Q, U, L,
```

**196/1 = 196 kHz 10 ms Total intensity**

```
my_spectra.clean(threshold=10) # first clean with threshold=10  
my_spectra.rm_baseline() # baseline flatening  
my_spectra.clean(threshold=4) # second and refined cleaning  
my_spectra.rm_baseline() # baseline refined flatening
```

```
#plot of the dynspectrum  
my_spectra.plot_dynspec()
```

**Plot dynspectra**






# NenuFAR waveform data with NenuRaw (dynamic spectrum)

## Python 3 script to plot the dynamic spectrum

```
> python3.8 /cep/lofar/pulsar/NenuRaw/demo/demo_storm_dynspectrum.py
```



# NenuFAR waveform data with NenuRaw (dynamic spectrum)

## Python 3 script to plot the dynamic spectrum

```
> python3.8 /cep/lofar/pulsar/NenuRaw/demo/demo_storm_pulse.py
```

```
if __name__ == "__main__":
    # wavfile (GUPPI or RAWTF format)
    files = ['/datafb2/nenufar-pulsar/ES03/2020/05/B0834+06_D20200510T1700_58979_250507_0069_BEAM1.0000.raw']

    # initialisation of the Dynspec object containing the methodes
    my_spectra = dynspec_utils.Dynspec(files,
        verbose=True,
        freq_start=0, #min freq allow
        freq_end=99, #max freq allow
        start=12.268, #start time in sec
        end=12.274 #stop time in sec
    )

    # force dm to 0 pc cm-3 or will use the dm from the header in PSR obs
    my_spectra.dm = 0


    # execution of the processing method in the Fourier domain creating 1 sub-c
    # and conversion to total intensity with time integration of 5.12 microsec
    my_spectra.fourier_computation(fftlens=1, ds_ms=0.00512, pol="I") #I, Q, U,

    my_spectra.clean(threshold=10) # first clean with threshold=10
    my_spectra.rm_baseline() # baseline flatening
    my_spectra.clean(threshold=4) # second and refined cleaning
    my_spectra.rm_baseline() # baseline refined flatening

    #plot of the dynspectrum
    my_spectra.plot_dynspec()
```

**196/1 = 196 kHz 5.12  $\mu$ s**

**Total intensity**






# NenuFAR waveform data with NenuRaw (dynamic spectrum)

## Python 3 script to plot the dynamic spectrum

```
> python3.8 /cep/lofar/pulsar/NenuRaw/demo/demo_storm_pulse.py
```





# NenuFAR waveform data with NenuRaw (dedisp dynspectrum)

## Python 3 script to plot the dedispersed dynspec

```
> python3.8 /cep/lofar/pulsar/NenuRaw/demo/demo_B0834+06_dynspec.py
```

```
if __name__ == "__main__":  
    # wavfile (GUPPI or RAWTF format)  
    files = ['/databf2/nenufar-pulsar/ES03/2020/05/B0834+06_D20200510T1700_58979_250507_0069_BEAM1.0000.raw']  
  
    # initialisation of my_spectra object containing the methodes  
    my_spectra = dynspec_utils.Dynspec(files,  
                                       verbose=True,  
                                       freq_start=0, #min freq allow  
                                       freq_end=99, #max freq allow  
                                       start=10, #start time in sec  
                                       end=20 #stop time in sec  
                                       )
```

```
# will use the dm from the header (can be changed with my_spectra.dm = X)
```

```
# initialisation of my_wav_obj object containing the Fourier methodes as coherent dedispersion
```

```
my_wav_obj = wav_utils.Wav()
```

```
my_spectra.new_fourier_methode(my_wav_obj.coherent_dedisp)
```

**Coherent de-dispersion**

```
# execution of the processing method in the Fourier domain creating 1 sub-channel
```

```
# and conversion to total intensity with time integration of 5.12 microsec
```

```
my_spectra.fourier_computation(fften=1, ds_ms=10, pol="I") #I, Q, U, L, V, X
```

**196/1 = 196 kHz    10 ms    Total intensity**

```
my_spectra.clean(threshold=10) # first clean with threshold=10
```


```
my_spectra.rm_baseline() # baseline flatening
```

```
my_spectra.clean(threshold=4) # second and refined cleaning
```

```
my_spectra.rm_baseline() # baseline refined flatening
```

```
#plot of the dynspectrum
```


```
my_spectra.plot_dynspec()
```



# NenuFAR waveform data with NenuRaw (dedisp dynspectrum)

**Python 3 script to plot the dedispersed dynspec**

```
> python3.8 /cep/lofar/pulsar/NenuRaw/demo/demo_B0834+06_dynspec.py
```






# NenuFAR waveform de-dispersion incoherent/coherent


B0809+74 de-dispersed

De-dispersion on total intensity



```
my_spectra.dedisperse(dm=my_spectra.dm)
```

De-dispersion on complex voltages



```
my_wav_obj = wav_utils.Wav()  
my_spectra.new_fourier_methode(my_wav_obj.coherent_dedisp)
```